

New Network Connectivity
User Guide
For
macOS/OSX

Contents:


- 1. Download software from IITR Network Support Portal.
- 2. Install software's as per guide instructions.
- 3. Configure Firefox changes. (Only if you use Firefox browser)
- 4. Restart the Mac.
- 5. Connect to new network (Wi-Fi or LAN).

Download Softwares


1.1 Go to https://www.iitr.ac.in/support and click on Network Support

Click

Here



1.2 Click on **Network Softwares**




Click Here

1.3 Click on Mac.



1.4 Click on **Network Connectivity Software** and **Network_Security_Setup_macos.zip** will be downloaded to your PC.




Choose Here

2.1 Extract Network_Security_Setup_macos.zip




2.2 Open the folder Network_Security_Setup_macos and install "Anyconnect Mobility Client".




2.3 Open **AnyConnect.pkg** and **Continue.**




2.4 Select the following packages (VPN selected by default, DART and ISE Posture) and click on Continue again.



2.5 Click on **Install** and proceed, later setup will ask you for your account password.




2.6 If prompted, please click on **Open Preferences** and **Allow** the software.






2.7 Install **Amp Connector** (Open Audit_fireampmac_Connector.pkg)




After clicking on **Continue** and **Agree to EULA**, click on **Install** to start installation, setup will ask for your account password.




2.9 If prompted please click on **Open Security Preferences** and click **Allow**.







2.10 Now run "run_it.command" file and provide password when asked.




3.1 Perform below steps only if you use **Firefox** browser else skip. Open Firefox browser and type "about:config" in address bar. Click "I accept the risk" and proceed.




3.2 Search of keyword "security.enterprise_roots.enabled" and make sure the Value is "true". If not proceed to the next step otherwise skip next step.



3.3 Right click on the attribute and select "Toggle" to change the value.




3.4 Finally make sure the value is set to "true".




Restart your MAC

4. Installation Completed, Restart your MAC.



Connect to new network (Wi-Fi & LAN)

5.1 After Restart open AnyConnect Secure Mobility Client and connect to ssid IITR_WIFI.



Connect to new network (Wi-Fi & LAN)

5.2 Provide your **username** & **password**. For faculties use Emp ID and for students use Enrollment Number as your initial username and password. Change it after first login.



Connect to new network (Wi-Fi & LAN)

5.3 Click **Continue** and provide **password**





For any query please contact network-support@iitr.ac.in

OR

Raise your ticket @ - https://network-support.iitr.ac.in/

Thank You

ICC, IITR

